

School-To-Home Connection

These installation instructions are for parents and guardians who have been notified by their school that *Lexia Reading*® can be used at home. (International users will see *Lexia Reading UK*). For assistance, please contact your student's school or district.

1. Can your computer run *Lexia Reading*?

Macintosh

- Mac OS X 10.4 or higher

Windows

- Windows XP (SP3), Vista, Windows 7 (Professional and Ultimate)

Additional System Requirements

- At least 256 MB RAM
- At least 500 MB hard drive space
- Speakers or headset (headset recommended)
- 32 MB accelerated video graphics card or better

Do you filter content on your home computer?


Please configure all content-filtering software, firewalls, and browsers on your home systems to allow access to *student.mylexia.com* and *update.lexialearning.com* via SSL (port 443).

2. Download *Lexia Reading* Installer

<http://www.lexialearning.com/support/lexiareading/license.html>


3. Install & Configure *Lexia Reading*

- a) **Windows:** Double-click the **Lexia Reading.exe** installer file that you downloaded.



You may receive a warning message from Windows, saying the publisher of the software is unknown. This is normal, and it is safe to click **OK** to continue with the install.


Follow the screen prompts until you see the **Customer Code** screen. Proceed to Step C.




Note: The Customer Code in this graphic is for example only. See the following page for your school's Customer Code.

For assistance with the installation and usage of Lexia Reading, please contact your child's school or district.

- b) **Macintosh:** Double-click the **Lexia** volume (or **Lexia UK**) that you downloaded. Drag and drop the Lexia icon from the left to the Applications folder on the right to install.



In the Applications folder, click the Lexia icon. The Settings screen displays.

A screenshot of the Lexia Settings application window. The window is divided into three sections: "General Settings", "Advanced Settings", and "Proxy Settings". In the "General Settings" section, the "Customer Code:" field is highlighted with a red rectangular box. Below it is a "Product Updates:" section with a "Install Update" button. The "Advanced Settings" section includes a "Server URL:" field with the text "https://student.lexia.com", and "Additional Options:" with checkboxes for "Full Screen (800 X 600)", "Check for Updates" (checked), and "Hide Password". There is also a "Network Request Timeout (Seconds)" field set to "120". The "Proxy Settings" section has fields for "Proxy Address:", "Proxy Port:", "Proxy User:", and "Proxy Password:", along with a "Prompt for Proxy Username & Password" checkbox. At the bottom of the window are "Save" and "Cancel" buttons.

- c) **Windows and Macintosh:** Type in the **customer code** you received from the school (include dashes).


Customer Code:	Please contact your Mini School for code
-----------------------	---

No other changes are recommended. Do **not** configure any proxy settings.

- d) **Windows:** Follow the screen prompts to complete the installation.
Macintosh: Click **Save** to close the Settings screen.

4. Using the *Lexia Reading* Student Software

- a) Double-click the *Lexia Reading* icon on your desktop to launch the software.
b) Your child will need to type in their username and password to start.

A screenshot of a "Student Login" window. It has a title bar with a lock icon and the text "Student Login". Below the title bar are two input fields: "Username:" with the text "Treet" entered, and "Password:". At the bottom right of the window is a green circular button with a white right-pointing arrow.

Note: *Lexia Reading* is intended for independent practice by the student with no assistance from parents or siblings. Please allow your child to work at their own pace without assistance.

For assistance with the installation and usage of Lexia Reading, please contact your child's school or district.